

Last update: August 08. 2022

Please note:

For WSXXX device versions ≥ 30 (see serial number)

[Get the newest release](#)

Release Notes

V 37 (08.08.2022)

- Bug fix: format error of channel parameter response for WMO_GUST_DIR channel, caused by missing WMO_GUST_DIR in advanced_info.c :: add_min_max()
- Manual (updated to v30): corrected transposed digits error in table 20.1, WMP_GUST_DIR line (german version)

V 36 (18.11.2021)

- Selectable handling of wind direction when wind speed below minimum: set 0.0 or hold last value
- Parallel operation of Modbus and analog frequency output enabled.
- Parallel analog output operation permitted except for protocols SDI12, Clipper and fullduplex operation
- Modbus message end detection changed from 3.5char timer to length prediction
- Permit parallel operation of Modbus and analog output (except frequency output)
- Corrected buffer length and send function for Modbus-ASCII (requires 510 chars buffer length)