

LinkComm Releases Notes

Status	RELEASE	Current FW Version	V4.1.1_r3
Owner	R&D / PM	Last Modified	September 09th, 2026

- Support for new XLink 2000!
- Improved SDI-12 setup on SL3/XL2 stations for a smoother sensor configuration experience
- Fixed SDI-12 template measurement parameter ordering on SL3/XL2
- Fixed ecoLog password input to prevent unsupported special characters
- Added clear success/failure when changing ecoLog passwords
- Fixed action configuration behavior on ecoLog/SensorLink devices
- Added support for "Client Only" certificate option for MQTT/TLS transmissions on SatLink3 and XLink 100/500 devices running firmware v886 or later
- Improved MQTT Broker configuration labels to provide clearer guidance when selecting Standard MQTT and Azure IoT Hub connection types while maintaining compatibility with existing firmware configurations.
- Firmware included: Satlink3 v886r4110, XLink 100/500 v886r4110, ecoLog 1000 v2.00.6, SensorLink 1000 v2.00.4