



SC4500 Software Package 1.68 – 2022.2

Release Notes

This document contains details about the latest release of SC4500

Release date: August 2, 2022

What's new – Probe support

Adding support of analog pH/ORP Module



The pH/ORP module for the SC4500 is a user or factory installed module that allows for the connection of an analog pH or ORP sensor to the controller. This module works with differential and combination pH and ORP sensors. See manual for additional connection information and sensor compatibility.

Adding support of Prognosys for UVAS Plus SC



Prognosys is a predictive diagnostic system that allows you to be proactive in your maintenance, by alerting you to upcoming instrument issues. Know with confidence whether changes in your measurements are due to changes in your instrument or your water. Prognosys is now available on SC4500 for UVAS Plus SC.

New firmware 1.00 for Profinet Hach Digital Output

- Increase measurement inputs from 8 to 32
- new GSDML file: GSDML-V2.4-Hach-SC4500-20220328.xml

New firmware 1.08 for EthernetIP Hach Digital Output

- Increase measurement inputs from 8 to 32
- new EDS file: Hach_SC4500_EtherNetIP_V108.eds

What's new – Improvements

Software package optimization

- 10% reduction in downloading and installation time

Bug fixes and stability Improvements

What's New – Claros

Improvement for Claros connected devices



Check this page for a full list of software releases, upgrades, and technical specifications for Claros, the Water Intelligence System from Hach.

<https://www.hach.com/claros/release-notes>

How to contact us

Website: <https://support.hach.com/app/ask>

North America

- Phone: 1- 800-227-4224 Option 2
- Email: techhelp@hach.com

Europe

- Phone: country specific
- Email: country specific