



SC4500 Software Package 3.43 – 2024.3

Release Notes

This document contains details about the latest release of SC4500

Release date: October 31st, 2024

What's new – Improvements

Feature Improvements

- PROFINET module has been recertified and minor issues on webserver have been fixed.

Package sensor

- Solitax package 18 (application version 2.29)
- Ultraturb package 12 (application version 3.10)

Bug fixes and stability improvements

- Modbus RS232/485 – in some rare circumstances, Modbus RS232/485 missed some SC4500 connected devices. The new module firmware version fixes this issue.

What's New – Claros

Improvement for Claros connected devices



Check this page for a full list of software releases, upgrades, and technical specifications for Claros, the Water Intelligence System from Hach.

<https://www.hach.com/claros/release-notes>

How to contact us

Website: <https://support.hach.com/app/ask>

North America

- Phone: 1- 800-227-4224 Option 2
- Email: techhelp@hach.com

Europe

- Phone: country specific
- Email: country specific